



# **Feature Description Document**

IXM WEB Installation Guide



### Purpose

This document outlines the process of installing, configuring the database for, and activating IXM WEB.

### **Applies to**

TITAN	TFACE	TOUCH 2	SENSE 2	MERGE 2	MYCRO
All Devices					

### Description

IXM WEB is a web-based, user-centric software application. Invixium provides a oneclick installation to set up IXM WEB that extracts all the necessary software and configures a database to start registering employees and devices.

IXM WEB is built using the Microsoft .NET Framework architecture, so it should only be used on Windows Operating Systems. IXM WEB cannot be installed on LINUX, MAC OS, etc. operating systems. Though, once IXM WEB is installed on a Windows Operating System, the user can browse the application from other operating systems as needed.

Invixium recommends setting up a few prerequisites before installing IXM WEB whether a user has a standalone or server Windows Operating System.



### **Supported Operating Systems**

IXM WEB operates on the following 32-bit and 64-bit operating systems:

(NOTE: Windows Home Premium, Professional or Enterprise versions only)

- ➢ Windows 8.1
- > Windows 10 (Build 1709 or higher) Professional Version
- Windows Server 2012 R2
- Windows Server 2012
- Windows Server 2016 Standard
- Windows Server 2019

Microsoft .NET Framework: .Net Framework 4.7.2.0

**Database Engine**: SQL Server 2014 Express Edition (Default Installation), SQL Server 2014 or higher

**IIS Internet Information Services**: Microsoft<sup>®</sup> Internet Information Services version 7.5 or higher

Installer: Windows<sup>®</sup> Installer (Installs Automatically) version 4.5 or higher



### **Before You Begin**

The following prerequisites ensure a smooth software installation:

- Windows Operating system needs to be up to date.
- System updates should not be pending. If any update is downloaded, the user will have to restart the system to complete the Windows update.
- The user who is setting up IXM WEB should have full administrator rights.
- Users should not use the HOME Edition of the Windows Operating System to install IXM WEB software.
- Invixium recommends following the guidelines provided for the user's operating system of choice.



### Request and Download the IXM WEB Setup File

- 1. Go to https://www.invixium.com.
- 2. Click IXM WEB to open the Menu >> Click GET IXM WEB.



3. Invixium recommends reading the instructions provided under the "**Before You Begin**" tab.



#### 4. Click the IXM WEB tab.

≡	Products	DAM WEB	About Us	Contact				INVIXIUM	×
		Bef	ore You Begin	XM WEB					
		IXM WEE Fill out the o Whor are Distribut Access End Use Custome	B Download ar tetalis below to rece you? tor Control Panel Manu Integrator er Details	d Activation te en email with steps to dow acturer	vribad, install and activate	POM WEE			
		Flesse prov issued in the First Nam	ide details of the En eir name and will pro	d-User who has purchased in wide them access to future up	wolum biometric solutions oprades and aupport. ast Nama*	and where they will be ins	tailed. The Activation License for IXM WE	5 wit be	
		Company	Name*	s	elect Country*	v	Phone Number*		

- 5. Provide the required details and click "**Submit**". An email with the latest IXM WEB package will be sent to the email provided.
- The user will receive an email from <u>support@invixium.com</u> that contains an IXM WEB Download link, Activation ID (this can be used later to activate IXM WEB online or offline), and instructions to activate IXM WEB through online or offline mode.

NOTE: please check your spam or junk folder if the below email doesn't appear in your inbox.



#### INVIXIUM



### 7. Right-click the **IXM WEB package** and extract the setup files to the machine.

Name	Date modified	Туре	Size
💢 IXMWeb 2.2.252.0	15-06-2022 17:55	Application	14,63,293 KB



### **Run IXM WEB Installation Setup**

1. Once **IXM WEB.exe** extracts, click **Install**. It will ask the user to accept the License Agreement.







- 2. Click "**Yes**" to accept the License Agreement. IXM WEB will then start the installation process.
- 3. By default, IXM WEB performs basic installation and installs software to the default location with the default port number. If the user wants to change the installation path, a port number that communicates with the IIS server is required. Click **Advanced** to view "Advanced Options".



- 4. In "Advanced Options", the user can change the following options:
  - Installation Path: In Basic Installation, the default path is "C:\Program Files (x86)\Invixium". By changing the path, the user can determine the new physical path on the machine where the IXM WEB package will be extracted.
  - **Port Number:** By default, the port number is "**9108**". Users can change the port number that is used to communicate between the WEB Server (Internet Information Services) and IXM WEB.
  - Install SQL Server: By default, this field is always selected. IXM WEB will install SQL Server 2014 Express Edition along with the IXM WEB XAD-FDD-611-03G

INVIXIUM



application. Users can uncheck this field if another version of SQL Server will be used or if a different machine will be used as a database server.

- Install Certificates: By default, the IXM WEB installer installs all the necessary certificates that are used in SSL communication, or specific certificates when IXM WEB is configured over the cloud. Users can uncheck this field to prevent IXM WEB from installing certificates. Invixium does not recommend deselecting this field.
- 5. Once all changes have been made, click **Install** to continue installing the package.





×

6. Once the installation process completes, the user can click **Complete** to finish.





7. IXM WEB will create a shortcut icon on the desktop.





## Configuring the IXM WEB Database

1. Double-click on the shortcut icon from the desktop to open IXM WEB in the default browser.

Authentication		SQL Server Name	
Windows	۲	IXM-LT-03\IXMWEB	•

- 2. IXM WEB will populate the default SQL Server name and SQL Server Instance.
- If the user wants to configure the database that is installed on another machine, then select the "SQL Server" option from the Authentication field. By selecting the "SQL Server" option, the user will be asked to add credentials (SQL User Name and Password) to connect to the Database Server machine.

	aniguning ixi	WEB DUIDDUSE	
Authentication		SQL Server Name	
SQL Server	•	IXM-LT-03\SQL2019	•
SQL User Name		Password	
admin		•••••	
9. Coppost			
& Connect	N		

#### INVIXIUM



- 4. If a user wants to use the database instance of the same machine, click **Connect** to verify that the connection is established with the SQL Instance.
- 5. Enter a new database name if there is no existing database available.

Authentication	SQL Server Name	
Windows	IXM-LT-03\SQL2019	•
IXMDB		•

6. Click Next.

	Chinguning IXM WEB	Database
Authentication	SQL	Server Name
Windows	• IXI	M-LT-03\SQL2019 +
Database Name		
IXMDB		
Confirm Password	Emo	alt.
		Cloud Port
Server URL		
Server URL http://localhost:9108		1255

INVIXIUM



- 7. Users can provide the necessary values to all the fields displayed under the "**Create Account**" section.
- 8. The fields and their functions are:
  - **Invixium ID:** Users can create a username that will have administrator rights to access any settings within IXM WEB. This ID should contain a minimum of 5 characters.
  - **Password:** Use this password to log in to IXM WEB with the above Invixium ID. While typing the password, IXM WEB will also display a strength rating to determine how secure the password is.
  - **Confirm Password:** Enter the password again.
  - **Email:** Set an administrator email address that IXM WEB will use in case the password needs to be reset or to send any email notifications.
  - Server URL: Users can input a Web URL or the IP Address of the machine where IXM WEB is installed along with the port number. The default port number is 9108.
  - **Cloud Port:** If a user wants to configure the devices over WEB Cloud, then a specific port number needs to be in the Cloud Port field. By default, the Cloud Port number is 1255.



9. Once the user is finished providing all the values, click **Save**.

dutthootication	SOL Server Norma
Windows	• IXM-LT-03\SQL2019 •
Database Name	
IXMDB	*
admin	Podsword Medium
Confirm Possword	Email
*********	support@Invixium.com
Sorvar URL	Cloud Port

10. Using the provided values, IXM WEB will create a database. Upon success, the user will be redirected to the Login Page.

Login Enter details bolow	2	~	•		
Enter INVIXIUM ID  Enter Password  Keep me Signed in  Sign In  Configure Email		Login Enter detaile	n s below		
Configure Email		Enter INVIXIUM ID			
Configure Emcil		Enter Password			
Configure Email		🗆 Keep me S	Signed In		
And the second		Con <mark>figur</mark> e Email	English	•	
You are currently using a 30-Day TIRAL varsion. To Activate IXM WEB, go to LICENSE -> Activate IXM WEB.	Sec.	You are currently using a 30-Day TRIAL v LICENSE -> Activat	arsion. To Activote IXM WEB, g e IXM WEB,	0 10	

INVIXIUM



## Activating IXM WEB Instance

1. On the login page, IXM WEB will display the highlighted message:

	×		
	Logir Enter datails	n below	•
	C Enter INVIXIUM ID		
	Enter Password		
	C Keep me S		
Conf	igure Empil	English	•



2. To activate IXM WEB, expand the **Left Navigation Panel** >> Click the **License** tab >> click **IXM WEB**.

×	2. B	🗶 IXM WE	в									1	🖁 💠 💽 admir
	Invixium Torunta, OH, Cunada	SUECTMODULE											
ß	Home	A		R		API	99			B	$\overline{\chi}_{\Lambda}$		
1	Vicieo Surveillance	IXM WEB	Connet	concerce of	2004 10000	104.40	1000 (Tenantin	(A-C) INTERIA	anticia	1000121004	Tables	Vitter	
500	Organization Hierarchy	SELECTLINK	3										
	logs		0										
۳3	Notification Settings	Supposer.	RS	nedap			STEMENS	Feenics	Paxton	LENEL S2	LENEL-S2	Harreywoll	Genetec
Q.	Link		Access III	401	convinue centre	any kellon	Fuelen	peep	11412	Teller	Orevers	Prevention	Security parmet
8	Uconso	SIEMENS		Huneyned									
1	Sync		System Centry	80.00									
12	General Settings	ACTIVATION HISTOR	er :										
<b>B</b> .	Company Schedule	Dato	r Modulo	Υ 000	oription	т Туро	τ. ο	rootod By	T lice	тна Тура	Y P	smolning	Station
×	Tools							0.00					4
	Roports							P.					
0	System						- (	*094					

3. If the machine where IXM WEB is installed has an internet connection, the user can activate IXM WEB using online mode.





4. Enter the Activation ID.

DXM WEB									
CT LINK									
Schpeider		Activation T	Activation	*			×	Netec	
VATION HISTOR	¥	Activation E	) NY-36-1E			✓ Act	ivate		
10	T Module				* Concel	<u></u>		io type	

5. If the machine where IXM WEB is installed does not have internet, then select the offline mode, enter the Activation ID, and click **Request**.

IK.	E IXM WEB Activation	8
	Activation Type Offline -	
	Activation ID [87-41-XO-NY-30-IE] Activation Key	✓ Request
1	* Concol	✓ Activate
		<u>)</u>



6. A popup window will be displayed with the machine details.

6		$\bigcirc$		$\odot$							
IOCM WEEK		CHILDONEED	DODY Allochin's	0.616.001	BOATS THE	(tooci: mier	000-000				
ACTION		-	Request				2				
Subjector Carne Color	R	Carritand D	Modulo Dox WEB OXI WEB Version 2.2.2.5.0 License Request WEB Activation			100 H	Genetec	SIEMENS			
TIVATION HISTOR	¥7		r –	0	MDUISIO KUY						
ota Y Modula Y		Y.			Activation ID			۲	Поонно дура		Y Remaining
			Sand above da	talls to support	@invieium.cor						
					- (0						

- 7. Copy this machine key and paste it into a new email to <u>support@invixium.com</u>.
- 8. When Invixium Support sends the license key, paste it in the "Activation Key" field and click **Activate**.
- 9. This success message will be displayed:





### Support

For more information relating to this Feature Description document, please contact us at <a href="mailto:support@invixium.com">support@invixium.com</a>

### **Disclaimers and Restrictions**

This document and the information described throughout are provided in their present condition and are delivered without written, expressed, or implied commitments by Invixium Inc. and are subject to change without notice. The information and technical data herein are strictly prohibited for the intention of reverse engineering and shall not be disclosed to parties for procurement or manufacturing.

This document may contain unintentional typos or inaccuracies.

### TRADEMARKS

The trademarks specified throughout the document are registered trademarks of Invixium Access Inc. All third-party trademarks referenced herein are recognized to be trademarks of their respective holders or manufacturers.

Copyright © 2023, INVIXIUM. All rights reserved.